

Models et numerical methodes in mechanics and physico-chemistry

Lecture 2. *Dislocation Dynamics*

Vladislav A. Yastrebov

*MINES ParisTech, PSL Research University, Centre des Matériaux, CNRS UMR 7633,
Evry, France*


@ Centre des Matériaux
February 8, 2016

Outline

- 1 Base des dislocations
- 2 Representation MD
- 3 Burgers vector
- 4 Contour method
- 5 Edge-screw types
- 6 Edge and screw in FCC, BCC and HCP
- 7 Cross-slip (glide and climb)
- 8 Mixed dislocations
- 9 Thermally activated mechanisms
- 10 Peierls stress
- 11 Stress field due to dislocation (Volterra dislocations)
- 12 Core vs elastic stress
- 1 MD simulations of dislocations? Limits
- 2 DD simulation of dislocations
- 3 2D vs 2.5D vs 3D
- 4 Existing DD codes
- 5 Computing driving forces at nodes
- 6 Limit contribution from a remote segment
- 7 Periodic BC
- 8 Fast Multi-pole
- 9 Viscous drag
- 10 Computing velocities
- 11 Computing displacements (trapezoidal Euler rule)
- 12 Topological changes
- 13 Literature (Bulatov & Cai, Kubin, Hull & Bacon, etc.)

Notion of plasticity


- Plasticity . . . irreversible change of shape
- In metals plasticity is the result of motion of linear defects of the crystal lattice: **dislocations**
- In rocks, for example, the plasticity is caused by slip at microcracks



Adapted from Wikipedia

Notion of plasticity


- Plasticity . . . irreversible change of shape
- In metals plasticity is the result of motion of linear defects of the crystal lattice: **dislocations**
- In rocks, for example, the plasticity is caused by slip at microcracks



Adapted from Wikipedia

Notion of plasticity


- Plasticity . . . irreversible change of shape
- In metals plasticity is the result of motion of linear defects of the crystal lattice: **dislocations**
- In rocks, for example, the plasticity is caused by slip at microcracks



Adapted from Wikipedia

Notion of plasticity

- Plasticity... irreversible change of shape
- In metals plasticity is the result of motion of linear defects of the crystal lattice: **dislocations**
- In rocks, for example, the plasticity is caused by slip at microcracks




Adapted from Wikipedia

Notion of plasticity


- Plasticity... irreversible change of shape
- In metals plasticity is the result of motion of linear defects of the crystal lattice: **dislocations**
- In rocks, for example, the plasticity is caused by slip at microcracks

Objective:

- Understand basics of dislocation motion
(✓ for DMS students)
- Convert this understanding into a computation model:
Dislocation Dynamics



Adapted from Wikipedia




from

[1] Bulatov V.V., Cai W. Computer Simulations of Dislocations, Oxford University Press, 2006.

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Square lattice

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Atoms arrangement

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Insert a half atomic layer
(line in 2D, plane in 3D)

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Obtain a dislocation defect

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Another option: let's shear this lattice

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



or rather push and pull along a particular plane

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Shift (make a step on left side)

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Of course the lattice deforms accordingly,
we can also imagine that we are far from free surfaces
(add transparent atoms)

Basic concept

- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...




Let's shear more

or we might keep the same shear and wait until thermal fluctuations of atoms make the dislocation to step one step further

Basic concept

- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...




It has just make one more step

The configuration is equivalent as if we introduced an
half atomic layer


Basic concept

- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...




Basic concept

- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D...



One more, and there is no more dislocations... but if we remove shear, an irreversible deformation remains in the system

Basic concept


- Dislocation is a line defect, a curve in a volume
- But the basics can be understood in 2D
- Carpet fold analogy



One more, and there is no more dislocations... but if we remove shear, an irreversible deformation remains in the system

Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers



Dislocation


Dislocation in 2D: Peierls potential

- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers




Dislocation in 2D: Peierls potential

- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential




Dislocation in 2D: Peierls potential

- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential



Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential



Array of potential wells and energy barriers (**Peierls potential**)


Dislocation in 2D: Peierls potential

- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential



Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion



Increasing temperature $k_B T$ increases the probability of jump

Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion



Increasing temperature $k_B T$ increases the probability of jump

Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion
- Interaction with free surface



Near the free surface, an energetically favorable direction of motion is towards the surface


Dislocation in 2D: Peierls potential

- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion
- Interaction with free surface



Dislocation in 2D: Peierls potential


- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion
- Interaction with free surface



Shear loading bias the potential and dictates the favorable direction of motion

Dislocation in 2D: Peierls potential



- Basics can be understood in 2D
- Concept of an array of potential wells and energy barriers
- Peierls potential
- Thermally activated motion
- Interaction with free surface
- Peierls stress



Increasing applied shear stress may result in a complete removing of the energy barrier (**Peierls stress τ_P**)


Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion




Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure




Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure



Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator




Dislocation is sensitive to the deviatoric part of the stress

$$s = \sigma - \frac{1}{3}\text{tr}(\sigma)I$$

$$\tau = n \cdot \sigma \cdot t = n \cdot s \cdot t$$

Dislocation in 2D: stress effects



- **Basics can be understood in 2D**
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses



Perfect crystal

Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses





Dislocation: crystal with an **inserted layer** of atoms

Tensile stress below $y < 0$: $\sigma_{xx} > 0$

Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses




Dislocation: crystal with a **removed layer** of atoms

Compressive stress above $y > 0$: $\sigma_{xx} < 0$

Dislocation in 2D: stress effects

- **Basics can be understood in 2D**
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects


● Inclusion particle



Inclusion on the glide line

Dislocation in 2D: stress effects

- **Basics can be understood in 2D**
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects




Interstitial defects migrate towards the zone of tensile stress induced by the dislocation

Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects

- Interstitial defect





Interstitial defects migrate towards the zone of tensile stress induced by the dislocation

[1] Cottrell & Bilby. Dislocation theory of yielding and strain ageing of iron. Proc Phys Soc A 62 (1949)

Dislocation in 2D: stress effects

- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects




Interstitial defects migrate towards the zone of tensile stress induced by the dislocation

[1] Cottrell & Bilby. Dislocation theory of yielding and strain ageing of iron. Proc Phys Soc A 62 (1949)

Dislocation in 2D: stress effects



- **Basics can be understood in 2D**
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects



Vacancy defects migrate towards the zone of compressive stress induced by the dislocation

Dislocation in 2D: stress effects



- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects
- Interactions between dislocations



Interaction of two “up” dislocations is repulsive

Dislocation in 2D: stress effects


- Basics can be understood in 2D
- Applied stress affects dislocation motion
- Rather insensitive to hydrostatic pressure
- Sensitive to the stress deviator
- Dislocation itself induces stresses
- Interactions with neighbouring defects: interstitial and vacancy defects
- Interactions between dislocations



Interaction of “up” and “down” dislocations is attractive and leads to annihilation of both defects


3D lattices

- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc)
(very rare for pure metals, *Po*)
 - body-centered (bcc)
(common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc)
(common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp)
(common, *Be, Mg, Zn, Ti*)
- + and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed)
($n \cdot d = ip + jr + ks = 0$)




3D lattices

- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc)
(very rare for pure metals, *Po*)
 - body-centered (bcc)
(common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc)
(common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp)
(common, *Be, Mg, Zn, Ti*)
- + and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed)
($n \cdot d = ip + jr + ks = 0$)



3D lattices


- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc)
(very rare for pure metals, *Po*)
 - body-centered (bcc)
(common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc)
(common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp)
(common, *Be, Mg, Zn, Ti*)
- + and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed)
($n \cdot d = ip + jr + ks = 0$)



3D lattices

- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc)
 - (very rare for pure metals, *Po*)
 - body-centered (bcc)
 - (common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc)
 - (common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp)
 - (common, *Be, Mg, Zn, Ti*)




+ and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed)
 - ($n \cdot d = ip + jr + ks = 0$)



3D lattices

- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc) (very rare for pure metals, *Po*)
 - body-centered (bcc) (common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc) (common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp) (common, *Be, Mg, Zn, Ti*)





+ and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed) ($n \cdot d = ip + jr + ks = 0$)



3D lattices


- Basics can be understood in 2D
- **But the complete picture can be drawn only in 3D**
- Crystallographic lattices in 3D:
 - primitive cubic (pcc) (very rare for pure metals, *Po*)
 - body-centered (bcc) (common, *Fe, Cr, W, Nb*)
 - face-centered cubic (fcc) (common, *Al, Cu, Au, Ag*)
 - hexagonal close packed (hcp) (common, *Be, Mg, Zn, Ti*)

+ and 10 other bravais lattices.
- Slip planes $n = (ijk)$ (often the most densely packed)
- slip systems $d = [prs]$ (often the most densely packed) ($n \cdot d = ip + jr + ks = 0$)



3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Box

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Introduce a cut along a densely packed plane with normal n (e.g. (111) in fcc)

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Introduce a cut along a densely packed plane with normal n (e.g. (111) in fcc)

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Cut's edge is the dislocation line,
introduce an orientation ξ

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Shift the cut by a vector b along the plane **orthogonally** to the dislocation line and glue sides
Edge dislocation

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Cut in the box

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Shift the cut by a vector b along the plane **parallel** to the dislocation line and glue sides
Screw dislocation

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Semi-circular cut in the box

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Shift the cut by a vector b and obtain a complex dislocation combining **screw and edge** dislocations

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Shift the cut by a vector b and obtain a complex dislocation combining **screw and edge** dislocations

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Edge dislocation

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Make a contour around
(right-hand rule *la règle de la main droite*)

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Make a contour around
(right-hand rule *la règle de la main droite*), compute the net Burgers vector

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Change the contour

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Make a contour around a dislocation free zone $b = 0$

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Screw dislocation

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Draw a contour:
4 down, 5 left, 4 up, 3 right

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



Draw a contour:
4 down, 5 left, 4 up, 3+2 right

3D dislocations


- Slip plane n
- Oriented dislocation line ξ
- Burgers vector b
can be expressed in terms of minimal distance between atoms in the slip system
- Dislocation types:
 - edge (*coin*): $b \cdot \xi = 0$
 - screw (*vis*): $b \times \xi = 0, \quad \forall n$
 - mixed
- Burgers circuit
provides the total Burgers vector within a contour
Attention: $b_T = 0$ does not imply that there is no dislocations



The Burgers vector is collinear with the dislocation line
 $b \parallel \xi$


Burgers circuit example

Example from the Monday lecture on Molecular dynamics



Burgers circuit example


Example from the Monday lecture on Molecular dynamics



Basal hcp (0001) or fcc slip plane (111)

Burgers circuit example


Example from the Monday lecture on Molecular dynamics



Contour 1: $b = 0$

Burgers circuit example


Example from the Monday lecture on Molecular dynamics



Contour 2: $b = \frac{a}{\sqrt{2}} [\bar{1}10]$

Burgers circuit example


Example from the Monday lecture on Molecular dynamics



Contour 2: $b = \frac{a}{\sqrt{2}}[\bar{1}10]$

Burgers circuit example

Example from the Monday lecture on Molecular dynamics




Contour 2: $b = \frac{a}{\sqrt{2}} [\bar{1}10]$

Forces on dislocations

- A uniform stress σ shears a single crystal
- Force on the top $f = \int \sigma \cdot n dA = \sigma_n w l$
- Work of this force on shearing the crystal by amount $b = e_1 |b|$:
$$W = f \cdot b = w l \sigma_n \cdot b$$
- At the same time dislocation of length w moves the distance l
- The “virtual” force f acting on the dislocation makes the same work:
 $w l f e_1 = W = w l \sigma_n \cdot b$ so
$$f = (\sigma_n \cdot b) e_1$$
- More generally (valid for edge and screw dislocations)

$$f = (\sigma \cdot b) \times \xi$$

(Peach-Koehler force)



Forces on dislocations

- Example: Frank-Read source in (111) plane with $b \sim [0\bar{1}1]$, e.g. $b = \frac{a}{2\sqrt{2}}(e_3 - e_1)$
- The box with this dislocation is under a uniaxial tension $\sigma = \sigma e_3 \otimes e_3$
- Let's compute the Peach-Koehler force as



$$f = (\sigma \cdot b) \times \xi$$

- Where $\sigma \cdot b = \sigma \frac{a}{2\sqrt{2}} e_3$

- At A: $\xi = \frac{dl}{\sqrt{2}}(e_1 - e_3)$, $df = -\sigma \frac{a}{4} e_2 dl$

at B: $\xi = \frac{dl}{\sqrt{2}}(e_2 - e_1)$, $df = -\sigma \frac{a}{4}(e_1 + e_2) dl$

at C: $\xi = \frac{dl}{\sqrt{2}}(e_3 - e_1)$, $df = \sigma \frac{a}{4} e_2 dl$



Note: line tension and self-interaction are not considered

Forces on dislocations

- Example: Frank-Read source in (111) plane with $b \sim [0\bar{1}1]$, e.g. $b = \frac{a}{2\sqrt{2}}(e_3 - e_1)$
- The box with this dislocation is under a uniaxial tension $\sigma = \sigma e_3 \otimes e_3$
- Let's compute the Peach-Koehler force as



$$f = (\sigma \cdot b) \times \xi$$

- Where $\sigma \cdot b = \sigma \frac{a}{2\sqrt{2}} e_3$

- At A: $\xi = \frac{dl}{\sqrt{2}}(e_1 - e_3)$, $df = -\sigma \frac{a}{4} e_2 dl$

at B: $\xi = \frac{dl}{\sqrt{2}}(e_2 - e_1)$, $df = -\sigma \frac{a}{4}(e_1 + e_2) dl$

at C: $\xi = \frac{dl}{\sqrt{2}}(e_3 - e_1)$, $df = \sigma \frac{a}{4} e_2 dl$



Note: line tension and self-interaction are not considered

Forces on dislocations

- Apart from the external load, dislocation has a **line tension** [J/m]
- Elastic energy per unit length stored around a dislocation (screw or edge)

$$E = \alpha\mu b^2, \quad \alpha \approx 0.5 - 1$$

- Line tension acting along the dislocation line is


$$T = \alpha\mu b^2$$

- So for curved dislocation of radius R :

$$Td\phi = \tau bdl = \tau bRd\phi$$



- For equilibrium (to keep this dislocation curved)

$$\tau = \alpha\mu b/R$$




Dislocation motion

- Recall the 2D case
- But dislocations are not point defect



Dislocation motion

- Recall the 2D case
- But dislocations are not point defect
- When the resolved shear τ is smaller than the Peierls stress τ_p , thermally activated motion propagate via **kinks**




Dislocation motion

- Recall the 2D case
- But dislocations are not point defect
- When the resolved shear τ is smaller than the Peierls stress τ_p , thermally activated motion propagate via **kinks**
- When $\tau > \tau_p$, dislocations glide in “viscous drag” regime, where dislocation velocity is proportional to the force as well as the lattice friction

$$v_{\text{dis}} \sim f_{PK}, \quad f_{fr} \sim -g(T)v_{\text{dis}}$$

- Friction force f_{fr} comes from thermal vibrations of the lattice (phonons)
- In FCC: often viscous drag regime
- In BCC: viscous drag for edge and kinks-mechanism for screw




Velocity wrt the applied shear stress
Adapted from

P. Haasen. *Physical Metallurgy*, Cambridge University Press (1996)


Dislocation motion II

- Note that the Peach-Koehler force is not in the slip plane
 $f_{PK} \cdot n \neq 0$
- Glide vs climb
- For edge dislocations:
glide conserves the number of atoms,
climb requires removing or adding lines of atoms (via, e.g. vacancies)
- Edge dislocations rather glide than climb at low temperature
- Very anisotropic motion
- Screw dislocation does not stick to a unique glide plane as $b \parallel \xi$
- Change of plane by screw dislocations results in **cross-slip**



Dislocation motion II


- Note that the Peach-Koehler force is not in the slip plane
 $f_{PK} \cdot n \neq 0$
- Glide vs climb
- For edge dislocations:
glide conserves the number of atoms,
climb requires removing or adding lines of atoms (via, e.g. vacancies)
- Edge dislocations rather glide than climb at low temperature
- Very anisotropic motion
- Screw dislocation does not stick to a unique glide plane as $b \parallel \xi$
- Change of plane by screw dislocations results in **cross-slip**



Screw dislocation may change the plane


Dislocation motion II

- Note that the Peach-Koehler force is not in the slip plane
 $f_{PK} \cdot n \neq 0$
- Glide vs climb
- For edge dislocations:
glide conserves the number of atoms,
climb requires removing or adding lines of atoms (via, e.g. vacancies)
- Edge dislocations rather glide than climb at low temperature
- Very anisotropic motion
- Screw dislocation does not stick to a unique glide plane as $b \parallel \xi$
- Change of plane by screw dislocations results in **cross-slip**



Dislocation-induced stress field

■ Volterra dislocation^[1]



Adapted from the MMC course
by Samuel Forest

■ Screw dislocation

$$\sigma_{xz} = -\frac{\mu b}{2\pi} \frac{y}{(x^2 + y^2)}$$
$$\sigma_{yz} = \frac{\mu b}{2\pi} \frac{x}{(x^2 + y^2)}$$


■ Edge dislocation

$$\sigma_{xx} = -\frac{\mu b}{2\pi(1-\nu)} \frac{y(3x^2 + y^2)}{(x^2 + y^2)^2}$$
$$\sigma_{yy} = \frac{\mu b}{2\pi(1-\nu)} \frac{y(x^2 - y^2)}{(x^2 + y^2)^2}$$
$$\sigma_{xy} = \frac{\mu b}{2\pi(1-\nu)} \frac{x(x^2 - y^2)}{x^2 + y^2}$$
$$\sigma_{zz} = \nu(\sigma_{xx} + \sigma_{yy})$$

[1] Volterra V. Sur l'équilibre des corps élastiques multiples connexes. *Ann. Sci. de l'Ecole Norm. Supér.* 24 (1907).

Dislocation-induced stress field

■ Volterra dislocation^[1]



■ Elastic energy per unit length for an edge and screw dislocation

$$E_e = \frac{\mu b^2}{4\pi(1-\nu)} \ln(R/r), \quad E_s = \frac{\mu b^2}{4\pi} \ln(R/r)$$


■ For a mixed dislocation (edge $b \sin(\theta)$, screw $b \cos(\theta)$)

$$E(\theta) = \frac{\mu b^2(1-\nu \cos^2(\theta))}{4\pi(1-\nu)} \ln(R/r) \approx \alpha \mu b^2, \quad \alpha \approx 0.5 - 1$$

[1] Volterra V. Sur l'équilibre des corps élastiques multiples connexes. *Annal. Sci. de l'Ecole Norm. Supér.* 24 (1907).

Interaction between dislocations

- Interaction between two edge **dislocations on the same line**
- Dislocations of the same sign repel because:
 - when close $E \approx \mu(2b)^2$
 - when far $E \approx 2\mu(b)^2$
- Dislocations of opposite sign attract because:
 - when close $E \approx \mu(b - b)^2 = 0$
 - when far $E \approx 2\mu(b)^2$



Interaction between dislocations

- Interaction between two edge **dislocations on parallel lines**
- Interaction energy is the work done by the stress field induced by 1 on displacing 2:

$$E_{\text{inter}} = \int_x^{\infty} (\sigma_{xy}b_x + \sigma_{yy}b_y + \sigma_{yz}b_z)dx = - \int_y^{\infty} (\sigma_{xx}b_x + \sigma_{xy}b_y + \sigma_{xz}b_z)dy$$


- The resulting forces for two parallel dislocation of the same sign
 $b_x^1 = b_x^2 = b$:

$$f_x = - \frac{\partial E_{\text{inter}}}{\partial x} = \frac{\mu b^2}{2\pi(1-\nu)} \frac{x(x^2 - y^2)}{(x^2 + y^2)^2}$$

$$f_y = - \frac{\partial E_{\text{inter}}}{\partial y} = \frac{\mu b^2}{2\pi(1-\nu)} \frac{y(3x^2 - y^2)}{(x^2 + y^2)^2}$$


Interaction between dislocations

■ Interaction between two edge dislocations on parallel lines




Interaction between dislocations

■ Interaction between two edge dislocations on parallel lines




Interaction between dislocations

- Interaction between two edge **dislocations** on parallel lines




Interaction between dislocations

- Interaction between two edge **dislocations on parallel lines**



Interaction between dislocations

- Interaction between two edge **dislocations on parallel lines**



Interaction between dislocations

- Interaction between two edge **dislocations on parallel lines**


from Marc Fivel (SiMap, INP Grenoble), www.numodis.fr/tridis

Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:


$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$

- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly



Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:
$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$
- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly




Interaction with a particle in dispersion-strengthened alloy

Orowan mechanism

Hirsch P.B., Humphreys F.J. Physics of Strength and Plasticity, Ed. A.S. Argon, MIT Press (1969)

Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:
$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$
- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly



Interaction with a particle in
dispersion-strengthened alloy

Hirsch mechanism (with cross slip)


Hirsch P.B., Humphreys F.J. *Physics of Strength and Plasticity*, Ed. A.S. Argon, MIT Press (1969)

Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:

$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$

- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly



Interaction with a particle in
dispersion-strengthened alloy

Hirsch mechanism (with cross slip)


Hirsch P.B., Humphreys F.J. *Physics of Strength and Plasticity*, Ed. A.S. Argon, MIT Press (1969)

Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:

$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$

- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly



Interaction with a particle in dispersion-strengthened alloy

Hirsch mechanism (with cross slip)

Hirsch P.B., Humphreys F.J. *Physics of Strength and Plasticity*, Ed. A.S. Argon, MIT Press (1969)

Dislocations interact with the environment

- **Free surface** $\sigma \cdot n = 0$
- To ensure zero stress vector, introduce an “image dislocation” of the opposite sign at the same distance from the surface:


$$(\sigma^{\text{real}} + \sigma^{\text{imag}}) \cdot n = 0$$

- Dislocations of opposite sign on the same line **attract each other**
- Note: an additional energy is needed to brake the oxide film
- **Rigid wall** $u = 0$, repulsion
- **Rigid inclusions** do not let dislocations glide quietly


*from Marc Fivel (SiMap, INP Grenoble),
www.numodis.fr/tridis*

Origin of dislocations

- In virgin well-annealed crystal
 $\rho \approx 10^{10} \text{ m}^{-2}$
- At early stages of deformation: single set of parallel slip planes is active
- At large deformation: $\rho \approx 10^{15} \text{ m}^{-2}$, different slip systems are activated
- At lattice defects and due to stress concentrators
- At grain boundaries
- Frank-Read sources (double and single ended)
- From the free surface
- Geometrically necessary dislocations to accommodate indenter's form



Single-ended Frank-Read source
from D. Hull, D.J. Bacon, *Introduction to Dislocations*, Elsevier (2011)



Double-ended Frank-Read source in silicon crystal
from Dash, *Dislocation and Mechanical Properties of Crystals*, Wiley (1957)


Origin of dislocations

- In virgin well-annealed crystal
 $\rho \approx 10^{10} \text{ m}^{-2}$
- At early stages of deformation:
single set of parallel slip planes is
active
- At large deformation: $\rho \approx 10^{15} \text{ m}^{-2}$,
different slip systems are activated
- At lattice defects and due to stress
concentrators
- At grain boundaries
- Frank-Read sources (double and
single ended)
- From the free surface
- Geometrically necessary dislocations
to accommodate indenter's form

DD simulation of double ended Frank-Read
source in a cube-shaped box with rigid walls

Origin of dislocations

- In virgin well-annealed crystal
 $\rho \approx 10^{10} \text{ m}^{-2}$
- At early stages of deformation: single set of parallel slip planes is active
- At large deformation: $\rho \approx 10^{15} \text{ m}^{-2}$, different slip systems are activated
- At lattice defects and due to stress concentrators
- At grain boundaries
- Frank-Read sources (double and single ended)
- From the free surface
- Geometrically necessary dislocations to accommodate indenter's form



Size effect in nano-indentation due to geometrically necessary dislocations

- [1] Nix, Gao. *J Mech Phys Solids* (1998)
[2] Swadener, George, Pharr. *J Mech Phys Solids* (2002)


Simulation of dislocations in 2D

2D DD^[1]

- Infinite straight and parallel dislocations
- No line tension
- No topological changes and intersections

Ingredients

- Only edge dislocations (points) randomly distributed on discrete slip lines
- Randomly distributed sources with stress and distance threshold:
 $|f| > f_{nuc}$: generates $\pm b$ dislocations at distance: $l_n = \mu b / [2\pi(1 - \nu)f_{nuc}]$
- On slip lines, randomly distributed obstacles with strength f_{obs}^i



R. Van der Giessen, A. Needleman. Discrete dislocation plasticity: a simple planar model. Model Sim Mater Sci Eng (1995)


Simulation of dislocations in 2D

2D DD^[1]

- Infinite straight and parallel dislocations
- No line tension
- No topological changes and intersections

Ingredients

- Only edge dislocations (points) randomly distributed on discrete slip lines
- Randomly distributed sources with stress and distance threshold:
 $|f| > f_{nuc}$: generates $\pm b$ dislocations at distance: $l_n = \mu b / [2\pi(1 - \nu)f_{nuc}]$
- On slip lines, randomly distributed obstacles with strength f_{obs}^i



R. Van der Giessen, A. Needleman. Discrete dislocation plasticity: a simple planar model. Model Sim Mater Sci Eng (1995)


Simulation of dislocations in 2D

2D DD^[1]

- Infinite straight and parallel dislocations
- No line tension
- No topological changes and intersections

Ingredients

- Only edge dislocations (points) randomly distributed on discrete slip lines
- Randomly distributed sources with stress and distance threshold:
 $|f| > f_{nuc}$: generates $\pm b$ dislocations at distance: $l_n = \mu b / [2\pi(1 - \nu)f_{nuc}]$
- On slip lines, randomly distributed obstacles with strength f_{obs}^i



R. Van der Giessen, A. Needleman. Discrete dislocation plasticity: a simple planar model. Model Sim Mater Sci Eng (1995)

Algorithm

- Impose an external stress field $\sigma^{ext}(x, y)$
- Find Peach-Koehler force on each source from external stress f_i^{ext} and from dislocations f_i^{cd}

- If $|f_i^{ext} + f_i^{cd}| \geq f_{nuc}$: create $\pm b$ dislocations

- Compute forces on all dislocations

$$f_j = - \sum \nabla_x E_{int}(x_i, x_j) + f_i^{ext}$$

- Assume linear relation between velocity and PK force:

$$f_j = B\dot{x}_j$$

- Integrate in time *Euler-trapezoid method*:

$$x_j^E(t + \Delta t) = x_j(t) + \frac{1}{B} f_j(x(t))$$

$$x_j(t + \Delta t) = x_j(t) + \frac{1}{2B} [f_j(x(t)) + f_j(x^E(t + \Delta t))]$$

Algorithm

- Impose an external stress field $\sigma^{ext}(x, y)$
- Find Peach-Koehler force on each source from external stress f_i^{ext} and from dislocations f_i^{cd}
- If $|f_i^{ext} + f_i^{cd}| \geq f_{nuc}$: create $\pm b$ dislocations
- Compute forces on all dislocations

$$f_j = - \sum \nabla_x E_{int}(x_i, x_j) + f_i^{ext}$$

- Assume linear relation between velocity and PK force:

$$f_j = B\dot{x}_j$$

- Integrate in time *Euler-trapezoid method*:

$$x_j^E(t + \Delta t) = x_j(t) + \frac{1}{B}f_j(x(t))$$

$$x_j(t + \Delta t) = x_j(t) + \frac{1}{2B} \left[f_j(x(t)) + f_j(x^E(t + \Delta t)) \right]$$


Simulation of dislocations in 3D

3D DD^[1]

- Splines or edge/screw segments
- Glide and climb
- Arbitrary morphology of dislocations
- Topological changes and intersections
- Enhanced interaction with the material and boundaries

Ingredients

- Frank-Read sources
- Free-surface
- Grain boundaries
- Possible coupling with the FEM method



Bulatov V.V., Cai W. *Computer Simulations of Dislocations*, Oxford University Press, 2006.

Simulation of dislocations in 3D

Algorithm

- Impose/compute via FEM a stress field $\sigma^{ext}(x, y)$

- Use shape functions for positions and velocities:

$$r(\xi, t) = N_i(\xi)r_i(t) \quad v(\xi, t) = N_i(\xi)v_i(t)$$

- Find Peach-Koehler force on each node from external stress f_i^{ext} and from all dislocation segments $f_i^d = - \int_{D_j} \nabla_x E_{inter} d\Gamma$

- Assume linear drag force:

$$f_j^{drag} = -B \cdot v_j$$

- Drag force cannot oppose everywhere the PK force, so it is satisfied in a weak sense:

$$\int_D N_i(-B \cdot v_j N_j + f^{PK}) dl = 0$$

- Giving the linear system of equations:

$$\sum B_{ij} \cdot v_j = f_i, \quad B_{ij} = \int_D -B N_i N_j dl$$

- Integrate in time *Euler-trapezoid method*:

$$x_j^E(t + \Delta t) = x_j(t) + v_j(t)\Delta t$$

$$x_j(t + \Delta t) = x_j(t) + \frac{1}{2}(v_j(t) + v_j^E(t + \Delta t))\Delta t$$

Animations <http://www.numodis.fr/>

References

- D. Hull and D.J. Bacon. Introduction to Dislocations, Elsevier (2011)
- J.P. Hirth and Jens Lothe. Theory of dislocations. (1982)
- Bulatov V.V., Cai W. Computer Simulations of Dislocations, Oxford University Press, 2006.
- <http://www.numodis.fr/>

- D. Hull and D.J. Bacon. Introduction to Dislocations, Elsevier (2011)
- J.P. Hirth and Jens Lothe. Theory of dislocations. (1982)
- Bulatov V.V., Cai W. Computer Simulations of Dislocations, Oxford University Press, 2006.
- <http://www.numodis.fr/>

Merci de votre attention !